

Aletheia Film Tools

Technical Reference & Development Documentation

Monos Pros Monon

2025

Contents

1	Introduction	3
1.1	System Architecture	3
1.2	Alpha — Color Space Bridge	3
1.2.1	Purpose	3
1.2.2	Source Code	3
1.2.3	Mathematical Foundation	3
1.2.3.1	Gamut Transformation	3
1.2.3.2	Supported Camera Gamuts	4
1.2.3.3	Log-to-Linear Transfer Functions	4
1.2.3.4	Negative Gamma Curves	5
1.2.4	Direction Modes	5
1.3	Phi — Primary & Secondary Grading	5
1.3.1	Purpose	5
1.3.2	Source Code	5
1.3.3	Mathematical Foundation	5
1.3.3.1	Printer Lights	5
1.3.3.2	Sigmoid Contrast	5
1.3.3.3	Smoothstep Blending	6
1.3.3.4	Skin Detection & Processing	6
1.3.3.5	Tetrahedral HSV Correction	6
1.4	Helix — Texture & Detail	6
1.4.1	Purpose	6
1.4.2	Source Code	6
1.4.3	Mathematical Foundation	6
1.4.3.1	Golden Angle Sampling	6
1.4.3.2	Clarity (Local Contrast)	7
1.4.3.3	Micro Contrast	7
1.4.3.4	Spatial Equalizer (6-Band)	7
1.5	Omega — Film Stock Emulation	7
1.5.1	Purpose	7
1.5.2	Source Code	7
1.5.3	Mathematical Foundation	8
1.5.3.1	H&D Curve (Hurter-Driffeld)	8
1.5.3.2	Spectral Dye Density	8
1.5.3.3	Film Stocks (42 Negatives, 19 Prints)	8
1.5.3.4	Dye Processes (10 Options)	9
1.5.3.5	Grain Model	9
1.5.3.6	Halation Model	9
1.6	Film Stock Tasting Notes	10
1.6.1	Motion Picture Negatives	10
1.6.1.1	Kodak Vision3 (2007–present)	10

1.6.1.2	Kodak ECN-II Historical (1974–2000s)	10
1.6.1.3	Kodak ECN-I Historical (1950–1974)	10
1.6.2	Still Photography	10
1.6.2.1	Kodak Portra	10
1.6.2.2	Fuji Professional	10
1.6.3	Reversal / Slide	10
1.6.4	Print Stocks	11
1.7	Pipeline Integration	11
1.7.1	Recommended Order	11
1.7.2	Color Space Flow	11
1.8	Technical Notes	11
1.8.1	GPU Acceleration	11
1.8.2	Data Sources	11
1.8.3	References	11

Chapter 1

Introduction

A comprehensive technical breakdown of the Aletheia color science pipeline: Alpha, Phi, Helix, and Omega. Each tool implements mathematically rigorous color transformations based on published research and manufacturer specifications.

1.1 System Architecture

Aletheia implements a complete film-style color pipeline:

Camera → Alpha → Phi → Helix → Omega → Display
 ↓ ↓ ↓ ↓
 [Gamut] [Grade] [Detail] [Film]

Alpha — Color space transformation (camera to grading space) **Phi** — Primary and secondary color grading
Helix — Texture and detail enhancement **Omega** — Film stock emulation with spectral accuracy

1.2 Alpha — Color Space Bridge

1.2.1 Purpose

Alpha converts between camera color spaces and a unified grading space, enabling consistent color science regardless of acquisition format.

1.2.2 Source Code

/01_OFX/03_Alpha/00_Source/Alpha.cpp

1.2.3 Mathematical Foundation

1.2.3.1 Gamut Transformation

Color space conversion uses 3×3 matrix multiplication through AP1 (ACES) as the connection space:

Output = [AP1→Output] × [Input→AP1] × Input

Matrix application:

```
inline void mtx(float* out, const float* in, const float* m) {
    out[0] = in[0] * m[0] + in[1] * m[1] + in[2] * m[2];
    out[1] = in[0] * m[3] + in[1] * m[4] + in[2] * m[5];
    out[2] = in[0] * m[6] + in[1] * m[7] + in[2] * m[8];
}
```

1.2.3.2 Supported Camera Gamuts

Gamut	Matrix to AP1
ARRI Wide Gamut 4	[0.6806687, 0.2363636, 0.0829677; ...]
ARRI Wide Gamut 3	[0.6954522, 0.1406787, 0.1638691; ...]
Sony S-Gamut3	[0.6387886, 0.2723514, 0.0888600; ...]
RED Wide Gamut	[0.7830944, 0.0868578, 0.1300477; ...]
DaVinci Wide Gamut	[0.7529825, 0.1433601, 0.1036573; ...]
ACES AP0/AP1	Direct passthrough

1.2.3.3 Log-to-Linear Transfer Functions

ARRI LogC4

```
float logc4_to_linear(float x) {
    float a = 2231.82630906769f, b = 64.0f;
    float c = 0.0740005604622393f;
    float s = 0.0181680833820122f, t = 0.0729553821550654f;
    if (x >= t)
        return (pow(2.0f, (x - c) / 0.0573514609390792f) - b) / a;
    return (x - t) / s;
}
```

ARRI LogC3 (EI 800)

```
float logc3_to_linear(float x) {
    float cut = 0.010591f;
    float a = 5.555556f, b = 0.052272f;
    float c = 0.247190f, d = 0.385537f;
    float e = 5.367655f, f = 0.092809f;
    if (x > e * cut + f)
        return (pow(10.0f, (x - d) / c) - b) / a;
    return (x - f) / e;
}
```

Sony S-Log3

```
float slog3_to_linear(float x) {
    if (x >= 171.2102946929f / 1023.0f)
        return pow(10.0f, (x * 1023.0f - 420.0f) / 261.5f) * 0.19f - 0.01f;
    return (x * 1023.0f - 95.0f) * 0.01125f / (171.2102946929f - 95.0f);
}
```

RED Log3G10

```
float log3g10_to_linear(float x) {
    float a = 0.224282f, b = 155.975327f;
    if (x < 0.0f) return x * 0.01f;
    return (pow(10.0f, x / a) - 1.0f) / b - 0.01f;
}
```

1.2.3.4 Negative Gamma Curves

Cineon (Printing Density) The classic film scan transfer function:

$\text{Linear} = (10^{((\text{Code} - 685) / 300) - 0.0108}) / (1.0 - 0.0108)$

ADX (Academy Density Exchange) ACES-standard negative density encoding.

1.2.4 Direction Modes

- **To Negative:** Camera → Digital → Negative Space (for grading)
- **To Digital:** Negative → Digital → Display (for viewing)

1.3 Phi — Primary & Secondary Grading

1.3.1 Purpose

Phi provides a complete color grading toolkit with printer lights emulation, tone mapping, skin processing, and tetrahedral color correction.

1.3.2 Source Code

/01_OFX/01_Phi/00_Source/Phi.cpp /01_OFX/01_Phi/00_Source/PhiKernels.metal

1.3.3 Mathematical Foundation

1.3.3.1 Printer Lights

Film-style color correction using multiplicative RGB scaling:

```
// Printer light: 2^(exposure/3) scaling
rgb.r *= pow(2.0f, printerR / 3.0f);
rgb.g *= pow(2.0f, printerG / 3.0f);
rgb.b *= pow(2.0f, printerB / 3.0f);
```

Each unit = 1/3 stop, matching traditional lab printer light values.

1.3.3.2 Sigmoid Contrast

Piecewise power function centered on pivot point:

```
float sigmoidContrast(float x, float contrast, float pivot) {
    if (x <= 0.0f) return 0.0f;
    if (x >= 1.0f) return 1.0f;

    // Scale x relative to pivot
    float t = x / pivot;
    float p = contrast;

    // Sigmoid: t^p / (t^p + (1-t)^p)
    float tP = pow(t, p);
    float omtP = pow(1.0f - t, p);
    return pivot * tP / (tP + omtP);
}
```

1.3.3.3 Smoothstep Blending

C1-continuous blending for smooth transitions:

```
float smoothstep(float edge0, float edge1, float x) {
    float t = clamp((x - edge0) / (edge1 - edge0), 0.0f, 1.0f);
    return t * t * (3.0f - 2.0f * t); // Hermite interpolation
}
```

1.3.3.4 Skin Detection & Processing

Biophysically-inspired skin tone processing using melanin and hemoglobin simulation:

```
// Kubelka-Munk model approximation
float melanin_absorption = melanin * (rgb.r * 0.1f + rgb.g * 0.3f + rgb.b * 0.6f);
float hemoglobin_response = hemoglobin * (rgb.r * 0.7f - rgb.g * 0.3f);

// Apply skin tone modification
rgb.r += melanin_absorption * skinDensity;
rgb.g += hemoglobin_response * skinRichness;
```

1.3.3.5 Tetrahedral HSV Correction

Six-vector color correction in tetrahedral space (Red, Green, Blue, Cyan, Magenta, Yellow):

```
// Determine which tetrahedron contains the color
if (r >= g && g >= b) {
    // Red-Yellow-White tetrahedron
    apply_red_yellow_correction(rgb, redHSV, yellowHSV);
} else if (g > r && r >= b) {
    // Yellow-Green-White tetrahedron
    apply_yellow_green_correction(rgb, yellowHSV, greenHSV);
}
// ... and so on for all 6 primary/secondary hues
```

1.4 Helix — Texture & Detail

1.4.1 Purpose

Helix enhances image texture through clarity, micro-contrast, and multi-scale spatial equalization.

1.4.2 Source Code

/01_OFX/02_Helix/00_Source/Helix.cpp /01_OFX/02_Helix/00_Source/HelixKernels.metal

1.4.3 Mathematical Foundation

1.4.3.1 Golden Angle Sampling

Fibonacci spiral pattern for artifact-free spatial sampling:

```
const float GOLDEN_ANGLE = 2.39996323f; // (3 - √5)

for (int i = 0; i < numSamples; i++) {
    float angle = GOLDEN_ANGLE * (float)i;
    float radius = sqrt((float)i / (float)numSamples);
```

```

    samples[i].dx = cos(angle) * radius;
    samples[i].dy = sin(angle) * radius;
}

```

1.4.3.2 Clarity (Local Contrast)

Unsharp mask in luminance channel with controlled radius:

```

float clarity = pixel_lum - local_average_lum;
output_lum = pixel_lum + clarity * amount;

```

The local average is computed using a weighted blur kernel at the specified radius.

1.4.3.3 Micro Contrast

Fine detail enhancement using high-frequency extraction:

```

// Extract fine detail at small radius
float fine_detail = pixel - blur_at_small_radius(pixel);

// Apply micro contrast enhancement
output = pixel + fine_detail * microAmount;

```

1.4.3.4 Spatial Equalizer (6-Band)

Multi-scale frequency decomposition with independent control:

Band	Description	Typical Radius
Z1	Ultra Fine	1-2 px
Z2	Fine	4-8 px
Z3	Medium	16-32 px
Z4	Coarse	64-128 px
Z5	Very Coarse	256-512 px
Z6	Ultra Coarse	1024+ px

Each band applies:

```

float band_detail = blur_at_radius[n] - blur_at_radius[n+1];
output += band_detail * band_gain[n];

```

1.5 Omega — Film Stock Emulation

1.5.1 Purpose

Omega renders the complete photochemical film look: negative stocks, dye processes, print stocks, grain, and halation. All stock parameters derived from manufacturer sensitometric data.

1.5.2 Source Code

```

/01_OFX/04_Omega/00_Source/OmegaPlugin.mm      /01_OFX/04_Omega/00_Source/OmegaKernel.metal
/01_OFX/04_Omega/03_Data/spectral_data.h /01_OFX/04_Omega/03_Data/film_stocks.h

```


1.5.3 Mathematical Foundation

1.5.3.1 H&D Curve (Hurter-Driffeld)

The characteristic curve maps scene luminance to film density:

Density = $f(\log(\text{Exposure}))$

Omega models this as a parametric sigmoid:

```
float hd_curve(float logE, float gamma, float shoulder, float ceiling, float black) {
    // Toe region
    float toe = black + (logE + offset) * toe_slope;

    // Linear region
    float linear = (logE - midpoint) * gamma;

    // Shoulder region (soft clip)
    float shoulder_val = ceiling - (ceiling - linear) * exp(-shoulder * (logE - shoulder_start));

    // Blend regions smoothly
    return blend_regions(toe, linear, shoulder_val, logE);
}
```

1.5.3.2 Spectral Dye Density

Each film stock has three dye layers (cyan, magenta, yellow) with wavelength-dependent absorption:

```
// From manufacturer spectral data
struct SpectralDensity {
    float wavelength[81]; // 380nm to 780nm, 5nm steps
    float cyan[81];
    float magenta[81];
    float yellow[81];
};
```

Color reproduction is computed by integrating the product of: - Scene spectral power distribution - Film sensitivity at each wavelength - Dye transmission at each wavelength

1.5.3.3 Film Stocks (42 Negatives, 19 Prints)

1.5.3.3.1 Motion Picture Negatives Kodak Vision3 5219 500T (2007)

ISO: 500

Balance: 3200K (Tungsten)

Gamma: 0.503

R/G/B Ceiling: [1.030, 0.996, 1.010]

R/G/B Multiplier: [1.034, 1.000, 0.906]

RMS Granularity: 5.08

Fuji Eterna 500T (2006)

ISO: 500

Balance: 3200K (Tungsten)

Exposure Base: 2 (not 10)

MTF at 50 lp/mm: ~0.35

Distinctive: Cooler palette, less saturation

1.5.3.3.2 Print Stocks Kodak 2383 Vision Print (1998)

LAD Values: [1.09, 1.06, 1.03]

Gamma: ~2.6 (theatrical projection)

D-min: [0.05, 0.05, 0.06]

D-max: [4.1, 4.2, 4.1]

1.5.3.4 Dye Processes (10 Options)

Process	Description
Neutral	No additional processing
Dye Transfer (Neg)	Technicolor IB from negative
Dye Transfer (K)	Kodachrome-style dye imbibition
Dye Transfer (Slide)	Transparency dye transfer
Radiance	Luminance-emphasized dye blend
Technicolor IV	1930s-1950s process
Technicolor V	1955-1975 process
Ilfochrome M	Cibachrome metallic
Ilfochrome P	Cibachrome pearl

1.5.3.5 Grain Model

Density-dependent grain using RMS measurements from manufacturer data:

```
// RMS varies with density (more grain in midtones)
float rms_at_density(float density, float* rms_curve, float* density_curve) {
    return interpolate(density, density_curve, rms_curve);
}
```

```
// Apply grain
float grain = gaussian_noise() * rms_at_density(pixel_density);
output = pixel + grain * grain_amount;
```

Film gauge affects grain size: | Gauge | Grain Scale | |———|—————| | 16mm | 1.5× | | 35mm | 1.0× | | 65mm | 0.7× |

1.5.3.6 Halation Model

Light scatter through film base, computed as exponential falloff blur:

```
// Separate highlights above threshold
float3 highlights = max(rgb - threshold, 0.0f);

// Apply exponential falloff blur
float3 halation = blur_with_kernel(highlights, halation_radius);

// Composite with film-base coloring (typically red-orange)
float3 halation_color = float3(1.0f, 0.4f, 0.1f); // From anti-halation dye
output = rgb + halation * halation_color * amount;
```

Three halation methods: 1. **Physical** — Yedlin-style emulsion scatter model 2. **Proosa** — Additive blend (faster) 3. **Minuth** — Frequency separation approach

1.6 Film Stock Tasting Notes

1.6.1 Motion Picture Negatives

1.6.1.1 Kodak Vision3 (2007–present)

5203 50D — ISO 50, Daylight *Character:* Crisp, clinical, modern. Finest grain in the Vision3 line. Exceptionally smooth highlight roll-off. *Best for:* High-end commercial, beauty, automotive.

5207 250D — ISO 250, Daylight *Character:* Balanced, versatile. ~14 stops dynamic range. The daylight workhorse. *Best for:* General narrative, documentary.

5213 200T — ISO 200, Tungsten *Character:* Warm, smooth. Creamy skin tones under tungsten. *Best for:* Studio work, tungsten-lit interiors.

5219 500T — ISO 500, Tungsten *Character:* Gritty, alive. Shadows retain detail, colors stay saturated. *Best for:* Night exteriors, available light.

1.6.1.2 Kodak ECN-II Historical (1974–2000s)

5247 II 100T — ISO 100, Tungsten, 1974 *Character:* Classic Hollywood warmth. Rich reds, deep blues. *Best for:* Period pieces (1970s-1990s).

5293 200T EXR — ISO 200, Tungsten, 1992 *Character:* The definitive 1990s film look. Warm but not orange. *Best for:* *Heat*, *Seven*, *Fight Club* era.

1.6.1.3 Kodak ECN-I Historical (1950–1974)

5247 100T — ISO 100, Tungsten, 1950 *Character:* Soft, pastel. The original Eastman Color look. *Best for:* *The Searchers*, *Rear Window*, *Vertigo* era.

1.6.2 Still Photography

1.6.2.1 Kodak Portra

Portra 160 — ISO 160, Portrait *Character:* Creamy, natural. Flattering skin tones. *Best for:* Portrait, wedding, fashion.

Portra 400 — ISO 400, Portrait *Character:* Versatile, warmer than 160. *Best for:* All-purpose professional photography.

Ektar 100 — ISO 100, Saturated *Character:* Punchy, vivid. Finest grain in consumer line. *Best for:* Landscape, product, travel.

1.6.2.2 Fuji Professional

Pro 400H — ISO 400, Portrait *Character:* Cool, ethereal. Pastel highlights. *Best for:* Wedding, editorial.

Eterna 500T — ISO 500, Motion Picture *Character:* Cool, clean. Less saturated than Kodak. *Best for:* Modern digital-era cinema aesthetic.

1.6.3 Reversal / Slide

Kodachrome 64 — ISO 64, K-14 *Character:* Rich, timeless. Unique dye-transfer colors. *Best for:* The National Geographic look.

Velvia 50 — ISO 50, E-6 *Character:* Hyper-saturated, contrasty. Legendary for landscapes. *Best for:* Nature when reality isn't colorful enough.

Provia 100F — ISO 100, E-6 *Character:* Natural, accurate. Faithful skin tones. *Best for:* Professional transparency work.

1.6.4 Print Stocks

Kodak 2383 — Vision Print (1998) *Character:* Contrasty, saturated. The theatrical reference. *Gamma:* ~2.6

Kodak 5381 — Color Print (1983) *Character:* Classic theatrical. Less contrast than 2383. *Best for:* 1980s-1990s theatrical aesthetic.

1.7 Pipeline Integration

1.7.1 Recommended Order

Alpha (input transform) →
Phi (primary grade) →
Omega Negative (film emulation) →
Helix (texture refinement) →
Omega Print (final look) →
Alpha (output transform)

1.7.2 Color Space Flow

1. **Alpha:** Camera log/gamut → ACEScct AP1
 2. **Phi:** Grade in ACEScct (exposure-linear feel)
 3. **Omega:** Emulate in linear AP1
 4. **Helix:** Detail work in log space
 5. **Alpha:** AP1 → Display (Rec.709/P3/2020 with gamma)
-

1.8 Technical Notes

1.8.1 GPU Acceleration

All plugins support Metal (macOS) and OpenCL acceleration: - **Metal:** Preferred on Apple Silicon, uses buffer-based OFX standard - **OpenCL:** Cross-platform fallback

1.8.2 Data Sources

- Spectral sensitivity: Manufacturer datasheets
- H&D curves: Published sensitometric data
- Dye densities: Spectrophotometer measurements
- Grain RMS: Manufacturer technical publications
- Matrix coefficients: ACES CTL transforms

1.8.3 References

- Kodak Essential Reference Guides for Sensitometry
 - Fujifilm Professional Motion Picture Product Data
 - ARRI Camera Color Science Documentation
 - ACES Technical Documentation (Academy)
 - Steve Yedlin ASC, “Display Prep Demo” and “Color Science for Filmmaking”
-

Aletheia Film Tools v1.0 All film stock data derived from manufacturer specifications and published research.